

Publicly Defined Classes, ReportPrinter Pro Version 3.0G. No attempt has been made to limit the list to "important" classes; all classes defined in the implementation sections of the RPPro units are included.

Class	Defining Unit	Ancestor Class
ERaveClass	RVDefine	Exception
ERAVECompiler	RVLEDef	Exception
ERaveException	RVUtil	Exception
EReportPrinter	RPDefine	Exception
TAddColumnForm	Rpaddfrm	TForm
TAnchorEditor	RVPEAnch	TForm
TArrayType	RVLEType	TBaseType
TBandStyleDialog	RVPEBand	TForm
TBaseID	RVLEID	TObject
TBaseMemoBuf	RPBase	TObject
TBaseReport	RPBase	TRPBaseComponent
TBaseShell	RPShell	TObject
TBaseType	RVLEType	TObject
TCanvasReport	RPCanvas	TBaseReport
TClassMember	RVLEType	TStructureMember
TClassType	RVLEType	TStructureType
TCodeManager	RVLECode	TObject
TColumnEditor	RPreG	TComponentEditor
TColumnEditorForm	RPCEDFRM	TDesignWindow
TConstID	RVLEID	TBaseID
TDataConnectFieldDef	RPCon	TObject
TDataConnectManager	RPCon	TObject
TDataConnectThread	RPCon	TThread
TDataMirrorEditor	RVPEDMS	TForm
TDataTextEditor	RVPEDTxt	TForm
TDBMemoBuf	RPDBUtil	TMemoBuf
TDBTableColumn	RPDBTabl	TTableColumn
TDBTablePrinter	RPDBTabl	TObject
TDetailShell	RPShell	TObject
TEnumeratedType	RVLEType	TBaseType
TErrorList	RVLEUtil	TObject
TExeForm	RPExeFrm	TForm
TExpression	RVLEExpr	TObject
TFieldNameProperty	RPreG	TStringProperty
TFilePreview	RPreview	TFilePrinter
TFilePrinter	RPFPrint	TCanvasReport
TFuncID	RVLEID	TBaseID
TFuncType	RVLEType	TBaseType
TIDManager	RVLEID	TObject
TImageEditor	RVPEImg	TForm
TLabelShell	rplabel	TObject
TMailMergeEditor	RVPEMail	TForm
TMasterKeyProperty	RPreG	TStringProperty

Class	Defining Unit	Ancestor Class
TMasterShell	RPShell	TObject
TMemoBuf	RPMemo	TBaseMemoBuf
TMemoEditor	RVPEMemo	TForm
TMethodID	RVLEID	TFuncID
TMethodMember	RVLEType	TClassMember
TMethodType	RVLEType	TFuncType
TModuleManager	RVLEMod	TObject
TModuleTypeHelper	RVLEMod	TTypeHelper
TNewFloatProperty	RPrep	TFloatProperty
TOpID	RVLEID	TBaseID
TPageListEditor	RVPEPLst	TForm
TPropertyMember	RVLEType	TClassMember
TRaveBand	RVCsRpt	TObject
TRaveBandStyle	RVCsRpt	TPersistent
TRaveBaseBarCode	RVCsBars	TRaveControl
TRaveBaseImage	RVCsStd	TRaveControl
TRaveBCDField	RVData	TRaveCurrencyField
TRaveBitmap	RVCsStd	TRaveGraphicImage
TRaveBlobField	RVData	TRaveDataField
TRaveBooleanField	RVData	TRaveDataField
TRaveCalcController	RVCsData	TRaveComponent
TRaveCalcOp	RVCsData	TRaveCalcVariable
TRaveCalcText	RVCsData	TRaveText
TRaveCalcTotal	RVCsData	TRaveCalcVariable
TRaveCalcVariable	RVCsData	TRaveComponent
TRaveCircle	RVCsDraw	TRaveEllipse
TRaveCode128BarCode	RVCsBars	TRaveBaseBarCode
TRaveCode39BarCode	RVCsBars	TRaveBaseBarCode
TRaveColorPropertyEditor	RVPEsSys	TRavePropertyEditor
TRaveCompiler	RVLEMod	TObject
TRaveComponent	RVClass	TObject
TRaveComponentEditor	RVTTool	TObject
TRaveComponentList	RVClass	TList
TRaveComponentPropertyEditor	RVTTool	TRavePropertyEditor
TRaveContainerComponent	RVClass	TRaveComponent
TRaveContainerControl	RVClass	TObject
TRaveControl	RVClass	TObject
TRaveCurrencyField	RVData	TRaveFormattedField
TRaveCursorPropertyEditor	RVPEsSys	TRavePropertyEditor
TRaveCustomText	RVCsStd	TRaveControl
TRaveDataBand	RVCsRpt	TRaveIterateBand
TRaveDataConnection	RVData	TObject
TRaveDataCycle	RVCsRpt	TRaveComponent
TRaveDataField	RVData	TRaveComponent
TRaveDataMemo	RVCsData	TRaveMemo
TRaveDataMirror	RVCsData	TPersistent

Class	Defining Unit	Ancestor Class
TRaveDataMirrorSection	RVCsData	TRaveSection
TRaveDataRow	RVDData	TObject
TRaveDataSystem	RVDData	TObject
TRaveDataText	RVCsData	TRaveText
TRaveDataView	RVDData	TObject
TRaveDateField	RVDData	TRaveDateTimeField
TRaveDateTimeField	RVDData	TRaveFormattedField
TRaveDelphiCompiler	RVLDComp	TRaveCompiler
TRaveDesigner	RVClass	TObject
TRaveEANBarCode	RVCsBars	TRaveBaseBarCode
TRaveEllipse	RVCsDraw	TRaveSurface
TRaveEnumPropertyEditor	RVTool	TRavePropertyEditor
TRaveEvent	RVClass	TObject
TRaveFiler	RVClass	TObject
TRaveFillStylePropertyEditor	RVPEsSys	TRaveEnumPropertyEditor
TRaveFloatField	RVDData	TRaveFormattedField
TRaveFloatPropertyEditor	RVTool	TRavePropertyEditor
TRaveFont	RVClass	TObject
TRaveFontMaster	RVCsStd	TRaveComponent
TRaveFontPropertyEditor	RVPEsSys	TRavePropertyEditor
TRaveFormattedField	RVDData	TRaveDataField
TRaveGotoPagePropertyEditor	RVPEsSys	TRaveComponentPropertyEditor
TRaveGraphicBase	RVCsDraw	TRaveControl
TRaveGraphicField	RVDData	TRaveBlobField
TRaveGraphicImage	RVCsStd	TRaveBaseImage
TRaveHLine	RVCsDraw	TRaveLine
TRaveI2of5BarCode	RVCsBars	TRaveBaseBarCode
TRaveIntegerField	RVDData	TRaveFormattedField
TRaveIntegerPropertyEditor	RVTool	TRavePropertyEditor
TRaveIterateBand	RVCsRpt	TObject
TRaveLine	RVCsDraw	TRaveGraphicBase
TRaveLockedPropertyEditor	RVPEsSys	TRaveEnumPropertyEditor
TRaveMailMergeItem	RVCsStd	TPersistent
TRaveMemo	RVCsStd	TRaveCustomText
TRaveMemoField	RVDData	TRaveBlobField
TRaveMetaFile	RVCsStd	TRaveGraphicImage
TRaveMethodList	RVClass	TList
TRaveMirrorPropertyEditor	RVPEsSys	TRaveComponentPropertyEditor
TRaveModule	RVClass	TObject
TRaveNamePropertyEditor	RVPEsSys	TRaveStringPropertyEditor
TRavePage	RVClass	TObject
TRavePageNumInit	RVCsStd	TRaveComponent
TRaveParser	RVLEUtil	TObject
TRavePasswordPropertyEditor	RVPEsSys	TRaveStringPropertyEditor
TRavePenStylePropertyEditor	RVPEsSys	TRaveEnumPropertyEditor
TRavePersistentList	RVClass	TList

Class	Defining Unit	Ancestor Class
TRavePip	RVClass	TObject
TRavePostNetBarCode	RVCsBars	TRaveBaseBarCode
TRaveProject	RPRave	TRPCComponent
TRaveProjectDesigner	RVTool	TRaveProjectEditor
TRaveProjectEditor	RPReg	TComponentEditor
TRaveProjectFileProperty	RPReg	TStringProperty
TRaveProjectItem	RVClass	TRaveContainerComponent
TRaveProjectManager	RVProj	TRaveProjectItem
TRavePropertyEditor	RVTool	TObject
TRaveReader	RVClass	TObject
TRaveRectangle	RVCsDraw	TRaveSurface
TRaveRegion	RVCsRpt	TRaveContainerControl
TRaveReport	RVProj	TRaveProjectItem
TRaveSection	RVCsStd	TRaveContainerControl
TRaveSimpleEvent	RVClass	TObject
TRaveSquare	RVCsDraw	TRaveRectangle
TRaveStackList	RVUtil	TList
TRaveStoreRAVProperty	RPReg	TStringProperty
TRaveStringField	RVData	TRaveDataField
TRaveStringPropertyEditor	RVTool	TRavePropertyEditor
TRaveSurface	RVCsDraw	TRaveGraphicBase
TRaveText	RVCsStd	TRaveCustomText
TRaveTimeField	RVData	TRaveDateTimeField
TRaveUnitsPropertyEditor	RVPEsSys	TRavePropertyEditor
TRaveUPCBarCode	RVCsBars	TRaveBaseBarCode
TRaveVariantPropertyEditor	RVTool	TRavePropertyEditor
TRaveVLine	RVCsDraw	TRaveLine
TRaveWriter	RVClass	TObject
TRCPUModule	RVLEMod	TObject
TRCPURunner	RVLERun	TObject
TRecordType	RVLEType	TStructureType
TReportEngineProperty	RPReg	TComponentProperty
TReportFiler	RPFiler	TBaseReport
TReportPrinter	RPrinter	TCanvasReport
TReportSection	RPSECT	TPersistent
TReportSectionProperty	RPReg	TClassProperty
TReportShell	RPShell	TObject
TReportShellProperty	RPReg	TComponentProperty
TReportSystem	rpsystem	TObject
TReprintLocsDialog	RVPERLoc	TForm
TRPAdvantageConnection	RPConAds	TRPCustomDataSetConnection
TRPBars2of5	RPBars	TRPBarsBase
TRPBarsBase	RPBars	TObject
TRPBarsCode128	RPBars	TRPBarsBase
TRPBarsCode39	RPBars	TRPBarsBase
TRPBarsEAN	RPBars	TRPBarsUPC

Class	Defining Unit	Ancestor Class
TRPBarsPostNet	RPBars	TRPBarsBase
TRPBarsUPC	RPBars	TRPBarsBase
TRPBaseComponent	RPBase	TRPComponent
TRPCanvas	RPDevice	TCanvas
TRPComponent	RPDefine	TComponent
TRPCustomConnection	RPCon	TObject
TRPCustomDataSetConnection	RPConDS	TRPCustomConnection
TRPDataSetConnection	RPConDS	TRPCustomDataSetConnection
TRPDevice	RPDevice	TObject
TRPFlashFilerConnection	RPConFF	TRPCustomDataSetConnection
TRPHalcyonConnection	RPConHy	TRPCustomConnection
TRPHTMLFiler	RPHTFiler	TBaseReport
TRPMidasConnection	RPConMid	TRPCustomDataSetConnection
TRPODBCExpressConnection	RPConOE	TRPCustomDataSetConnection
TRPPreviewForm	RPPREFRM	TForm
TRPQuery400Connection	RPCon400	TRPCustomDataSetConnection
TRPQueryConnection	RPConBDE	TRPCustomDataSetConnection
TRPSetupForm	RPSETFRM	TForm
TRPStatusForm	RPSTAFRM	TForm
TRPStringObject	RPDefine	TObject
TRPTable400Connection	RPCon400	TRPCustomDataSetConnection
TRPTableConnection	RPConBDE	TRPCustomDataSetConnection
TRPTopazConnection	RPConTZ	TRPCustomDataSetConnection
TRTFFiler	RPRTFiler	TBaseReport
TRvWzMDForm	RVWzMD	TForm
TRvWzSimpleForm	RVWzSimp	TForm
TScopeManager	RVLEMod	TObject
TSectionEditForm	rpsecfrm	TForm
TSimpleType	RVLEType	TBaseType
TStreamHelper	RVUtil	TObject
TStringsDialog	RVPEStrL	TForm
TStructureMember	RVLEType	TObject
TStructureType	RVLEType	TBaseType
TSystemFiler	rpsystem	TPersistent
TSystemPreview	rpsystem	TPersistent
TSystemPrinter	rpsystem	TPersistent
TTableColumn	RPTable	TObject
TTableItem	RPTable	TObject
TTablePrinter	RPTable	TObject
TTablePrinterProperty	RPReg	TComponentProperty
TTableRow	RPTable	TObject
TTableSection	RPTable	TObject
TTextFiler	RPTXFiler	TBaseReport
TTypeHelper	RVLEType	TObject
TTypeID	RVLEID	TBaseID
TTypeManager	RVLEType	TObject

---

Class	Defining Unit	Ancestor Class
TVarID	RVLEID	TBaseID

Count: 228